


Download Linkly Software from <https://www.linkly.com.au/resources-support/software>

Begin installation:



**License Agreement**

Please read the following important information before continuing.



Please read the following License Agreement. You must accept the terms of this agreement before continuing with the installation.

End-User Licence Agreement - LINKLY Pty Ltd ACN 099 609 284

This End-User Licence Agreement ("EULA") is a legal agreement between you and LINKLY Pty Ltd ACN 099 609 284 ("LINKLY") that covers the LINKLY software product, including any subsequent versions, updates or enhancements ("Software"). By accessing or otherwise using any LINKLY Software, you agree to be bound by the terms of this EULA. If you do not agree to be bound by the terms of this EULA, do not use any LINKLY Software. This EULA does not grant you any other rights but for the ones contained herein.

1. GRANT OF LICENCE: This EULA grants you the right to use the Software only for its intended purpose. You may not sell, resell, licence, rent, lease, lend, or otherwise transfer for value, the use of or installation of the Software. You may not reproduce or redistribute the Software in any form or broadcast it in any media.

2. JOINT RESPONSIBILITIES: Each party represents and agrees:

(a) that it has full power and authority necessary to validly enter into and perform all of its obligations under this Agreement; and

(b) to comply with the other party's reasonable security, confidentiality and operational requirements of which it has been given reasonable notice


I accept the agreement

I do not accept the agreement

< Back

Next >

Cancel



Select *Offline Development*.

**Select The Install Configuration**

Which configuration of Linkly do you wish to install?



Linkly Client And Server: Select this option if a PINpad will be attached to this PC. This option will allow you to configure your PINpad as well as your connection to the bank.

EFT-Server Only: Select this option if a PINpad will not be attached to this PC. This option will allow you to configure your connection to the bank.

Offline Development: Select this option if you are installing the offline development system on this machine. No connection to the bank can be configured.

Linkly Client And Server (A PINpad will be attached to this PC)

Linkly Client And Server (A PINpad will be attached to this PC)

Server Only (A PINpad will not be attached to this PC)

Offline Development

< Back

Next >

Cancel



### Ready to Install

Setup is now ready to begin installing Linkly on your computer.




Click Install to continue with the installation.

After the software has been installed the Linkly Configuration Wizard will open to guide you through the configuration process.

< Back

Install

Cancel



The following window will open:

It is not required for Offline Development, so click exit.


## Introduction

Exit Configuration Wizard


Exit the Configuration Wizard?

 YES (F3) NO (ESC) **Exit** **Restart** **Skip** **Next**


This will complete the installation and then open the Virtual Pin Pad:



Go to your system tray and open the Client:




In COM Port, type “TCPIP” and click apply, then close.



Next, you will need to restart the Linkly Client on Windows Services.

To do this, search for "Services" on your windows search bar and click on icon:




Scroll through and find “Linkly Client”.

Right Click and select restart.


Service Name	Description	Start Type	Current State	Log On Type	Local System...
Link-Layer Topology Discov...	Creates a N...	Manual	Local Service		
Linkly Client	Start	Running	Automatic	Local Syste...	
Local Profil...	Stop	Stopp...	Running	Manual (Trig...	Local Service
Local Sessio...	Pause	ndo...	Running	Automatic	Local Syste...
MessagingS...	Resume	up...		Manual (Trig...	Local Syste...
Microsoft (L...		atics ...		Manual	Local Syste...
Microsoft A...	Restart	use...		Manual (Trig...	Local Syste...
Microsoft A...	All Tasks	s A...		Disabled	Local Syste...
Microsoft C...		s int...		Manual	Network S...
Microsoft E...	Refresh	icr...		Manual	Local Syste...
Microsoft E...	Properties	our ...		Disabled	Local Syste...
Microsoft E...		our ...		Disabled	Local Syste...
Microsoft i...	Help	s In...		Manual	Local Syste...
Microsoft Keyboard Filter	Controls ke...			Disabled	Local Syste...

Recheck your system tray and you should be able to see the client (indicated by the letter "C") go from Yellow to Green. This means that the client is connected.

Before –




After –




Next,

Go to C:\PC\_EFT\DevTools\IPInterface.TestPOS and open *IPInterface.TestPOS* application:


Click *Connect* on the settings pane.




Then click *Logon*:



It will display this message:




And the Virtual Pin Pad will show you the following:




This means you are now connected successfully.

To test a transaction, try the following:

Click 'Transaction' in the Test Pos application's navigation pane and then click Transaction at the bottom:



This will send a Transaction request to the Virtual Pin Pad:



Follow the prompts on the virtual pin pad to complete the transaction:







The transaction is complete.